

Twilio Permission	Method	Endpoint	API Doc
/twilio/iam/api-keys/create	POST	https://iam.twilio.com/v1/Keys	API Doc
/twilio/iam/api-keys/update	POST	https://iam.twilio.com/v1/Keys/sid<SK>	API Doc
/twilio/iam/api-keys/read	GET	https://iam.twilio.com/v1/Keys/sid<SK>	API Doc
/twilio/iam/api-keys/list	GET	https://iam.twilio.com/v1/Keys	API Doc
/twilio/iam/api-keys/delete	DELETE	https://iam.twilio.com/v1/Keys/sid<SK>	API Doc
/twilio/iam/accounts/read	GET	https://api.twilio.com/2010-04-01/Accounts/sid<AC>	API Doc
/twilio/iam/accounts/list	GET	https://api.twilio.com/2010-04-01/Accounts	API Doc
/twilio/iam/public-keys/create	POST	https://accounts.twilio.com/v1/Credentials/PublicKeys	API Doc
/twilio/iam/public-keys/update	POST	https://accounts.twilio.com/v1/Credentials/PublicKeys/sid<CR>	API Doc
/twilio/iam/public-keys/read	GET	https://accounts.twilio.com/v1/Credentials/PublicKeys/sid<CR>	API Doc
/twilio/iam/public-keys/list	GET	https://accounts.twilio.com/v1/Credentials/PublicKeys	API Doc
/twilio/iam/public-keys/delete	DELETE	https://accounts.twilio.com/v1/Credentials/PublicKeys/sid<CR>	API Doc
/twilio/iam/credentials-aws/create	POST	https://accounts.twilio.com/v1/Credentials/AWS	API Doc
/twilio/iam/credentials-aws/update	POST	https://accounts.twilio.com/v1/Credentials/AWS/sid<CR>	API Doc
/twilio/iam/credentials-aws/read	GET	https://accounts.twilio.com/v1/Credentials/AWS/sid<CR>	API Doc
/twilio/iam/credentials-aws/list	GET	https://accounts.twilio.com/v1/Credentials/AWS	API Doc
/twilio/iam/credentials-aws/delete	DELETE	https://accounts.twilio.com/v1/Credentials/AWS/sid<CR>	API Doc